



The update procedure through OTA – Allview P7 Lite SV16.0 / Android 7.0 / 09.05.2018



The software update advantages are:

- ✓ *software stability improvement;*
- ✓ *self-improvement;*



ATTENTION! *The phone must be fully charged when initializing the procedure.*




ATTENTION! *Please do not stop the update operation under any circumstance.
The software update is an operation made on own responsibility by following the steps below.*




To update the software version of the *Allview P7 Lite* smartphone please follow the next steps:

1. Turn on the phone and connect it to a wireless network.
2. Make sure you have the SD Card inserted in phone and selected as the default location writing.






3. Open the "Update OTA" app from the apps menu:






4. In “**System Update**” app check for new software version (**P7_Lite_SV16.0**). Click on **Download**:






5. Please wait for the full software download in the phone's storage (micro SD card).






6. After the full software download, a message that will inform you about this update will be displayed on the phone's screen:




7. Select **Done**. The phone will reboot and the update procedure will automatically start.





8. After finishing the update process, the phone will reboot itself.



9. **“Android is upgrading”** message will be displayed on the phone’s screen.

The update file downloaded in the phone's storage (micro SD card) will be automatically deleted after the termination of the update process.