



The software update procedure - Allview Viva i10G/ 15.04.2015



ATTENTION! The tablet must be fully charged when initializing the procedure.



ATTENTION! Please do not stop under any circumstance the update operation.

The software update is an operation which is realised on own responsibility by following the steps below.




ATTENTION! This update procedure is applied only to the Viva i10G tablets that come with the Jelly Bean 4.2 operating system (This information can be verified in **Settings-> About tablet -> Android Version 4.2**).

To update the software version of the **Allview Viva i10G** tablet it is necessary to follow the next steps:

1. Download the **"Update_Viva_i10G_KitKat_15.04.2015.zip"** archive on a desktop PC or a laptop.




2. Copy the **“Update_Viva_i10G_KitKat_15.04.2015.zip”** archive on the internal storage or on a microSD card.
3. Turn on the tablet and open the **System Update** app from the app menu:






4. Press the app's "**Local Update**" option.






5. Select the update file from the internal storage or from the microSD card:
"Update_Viva_i10G_KitKat_15.04.2015.zip".






6. A message will be displayed on the tablet's screen that will inform you about this update:






7. Select **Update**. After the tablet will check the update file, it will restart itself and it will start automatically the update procedure.





8. The update procedure will be pointed by a status bar.



9. After the update process is finished, the tablet will reboot.



We recommend **Factory Reset** after the update to avoid some errors.



ATTENTION! The tablet's factory reset will completely delete your personal information and all the apps installed on the tablet.